

Install DNS Server on NT Server

INSTALLATION:

(If Exchange is running on this server, stop the Exchange Services.)

1. Right click Network Neighborhood, choose Properties.
2. Choose the Services tab.
3. Click Add.
4. Choose Microsoft DNS Server, click OK.
5. When prompted, put in the path of the NT server files.
6. Click Continue after entering the path.
7. Click Close.
8. Restart the server after install finishes.
9. Apply SP6a.
10. Restart the server

CONFIGURATION OF DNS SERVICES:

1. Click Start, Programs, Administrative Tools (Common), DNS Manager.
2. Click DNS, New Server.
3. Enter the IP number of the Exchange/NT server, click OK.
4. Highlight the IP number of the Exchange/NT server and click DNS, New Zone.
5. Choose **Secondary**. For **Zone**, enter district.k12.ky.us. For **Server**, enter the IP address of the district Exchange/NT server.
6. Click Next.
7. Click in **Zone File** field (it will populate itself).
8. Click Next.
9. At IP Master(s), enter 10.16.1.1, click Add.
10. Click Next.
11. Click Finish.
12. Highlight the server name, click DNS, Properties.
13. Choose the Forwarders tab.
14. "Check" the **Use Forwarders** box.
15. Enter the primary Internal DNS server IP address, 10.16.1.1, and click Add.
17. Leave the **Forward Time Out** set at 0 seconds.
18. Click OK when finished.
19. Exit DNS Manager when finished.